## Weiss DAC EQ curves

- 1. Open the DAC's web interface by putting the ip address of the unit into a web browser once it's plugged into your network.
- 2. On the main page, scroll down to the "DSP Plugins" portion and select "Headphone EQ"

DAC502 web interface 44.1 KHz		V w	
Volume			
		-60	al ×
Balance			
		Center	
Input Source		Active Output	
XLR RCA TOS USB UPnP Roon Ready		<b>1</b> 0	Ģ
Output Level		Output Polarity	
0 dB -10 dB -20 dB -30 dB		Normal	Inverted
DSP Plugins			
0 DeEsser 0 Vinyl 0 E0 0 Hea	dphone EQ 🕜 Loudness EQ 🕜 Dynamics	C Crossfeed HP	
Headphone EQ equalize characteristics of selected head Enable Bypass	phone models		
Model	Audeze LCD-XC	$\checkmark$	

3. Click "Enable", and then set your EQ curve for your specific Audeze headphones:





If you don't see these options, you may need to update your Weiss DAC firmware. You can do that by clicking the "Check for Update" button below the DSP Plugins.